


Q: How to disable and remove the Switch All Button in the APP from the SA-102.

A: The default setting for the SA-102 will display 3 Buttons in the APP, Button S1, Button S2 and Button Switch All. The Switch All button switches S1 and S2 at the same time. When you do not want to use this button and remove it from the APP. Then this is possible.

In the Airlive SmartLife Plus APP go to the SA-102 In-Wall Switch, it does not matter which of the 3 buttons you select. You can choose either of them.



In the In-Wall Switch setup go to “Config” by clicking on the >> .

Enter the Param: 10

Enter the Value: 2 (the default value is 1)

Enter the Size: 1

Now press “Write” the new settings will added. To check if the writing was successful enter only 10 at Param and press “Read” when the Value now shows 2 it means it was changed successful. The Switch All Button of the In-Wall is now disabled. When you also want to remove it from the APP. You would need to Exclude and Include the In-Wall Switch again. Ones this is done only Button S1 and Button S2 will be shown.

